

CS 1550

Week 12 – Project 4

Teaching Assistant
Xiaoyu(Veronica) Liang

• FUSE is a **Linux kernel extension** that allows for a user space program to provide the implementations for the various file-related syscalls

Goal: Use FUSE to create our own file system

Installation of FUSE

- Kernel is installed
- Install libraries and example programs

```
cd /u/OSLab/USERNAME

cp /u/OSLab/original/fuse-2.7.0.tar.gz .

tar xvfz fuse-2.7.0.tar.gz

cd fuse-2.7.0
./configure

This compiles the examples.
```

Setting up the Environment Variables

- cd ~
- chmod u+w .bash_profile
 Gives you the write permission to .bash_profile
- nano .bash_profile
- Scroll down to the end of the file until you see the line:
 "# Define your own private shell functions and other commends here"
- Add the following lines (spacing around '[' and ']' characters need to be there!)
 if ["\$HOSTNAME" = "thoth.cs.pitt.edu"]; then
 source /opt/set_specific_profile.sh;
 fi
- Save the file and quit
- chmod u-w .bash_profile
- .bash_profile will not run until the next time you log in
- source /opt/set_specific_profile.sh

FUSE Example

- cd fuse-2.7.0/example
- mkdir testmount (create mount point)

A mount point is a location in the UNIX hierarchical file system where a new device or file system is located


- Is -al testmount Empty, only see: . and ..
- ./hello testmount
- Is -al testmount Should see 3 entiries: ., .., hello
- fusermount –u testmount

Unmount the file system we just used when we are done, or need to make changes to the program.

Always need to do unmount!

Debug Mode

- Testing is to launch a FUSE application with the –d option
 - ./hello –d testmount
 - This will keep the program in the foreground, and it will print out every message that the application receives, and interpret the return values that you're getting back.
- Open a second terminal window and try your testing procedures.
- If you do a CTRL + C in the first window, you may not need to unmount the file system.
- IMPORTANT: if your program crashes or you abort it, you definitely need to do the fusermount. Otherwise, you will get a confusing "Transport endpoint not connected" message the next time you try to mount the system.



ls cat echo ••• User

Will only work within the mount point folder

hello.c

Kernel

FUSE

